

## Updating EXA accessory firmware.

(using Nordic Semiconductor tools)

You can check current firmware version using RFIDDemo→About→Attached reader Info: Accessory.

RFIDDemo application is another way to perform firmware update but if not available you can follow this instruction for secured DFU update using Nordic Semiconductor software.

Needed mobile software: (from Android PlayStore or from App Store for iOS devices)

**“nRF Connect for Mobile”**


### Setting device to boot mode:

- **Power off device.**
- **Press and keep trigger button down -->** -blue led blinks rapidly.
- **Press both: POWER and PAIR button down and then release.** → Left and right led's are on.
- **Release trigger** → Device is now in boot mode and advertises itself as “DfuNid” or "DfuEXA". If no DFU connection within 90 sec, device restart normally.


### Updating Firmware:

-Open “nRF Connect” application from your mobile phone. (Make sure Bluetooth is enabled)


-“DfuNid” or "DfuEXA" should appear in the list. → Press “Connect”



after successful connection, following screen appears. Press DFU as pointed below:



Select Distribution packet (ZIP) and browse to firmware file:



follow updating procedure.

After DFU procedure, all led goes off and it takes about 30 sec before device restart so please be patient.